

## [New 300-115 Dumps Full Version 300-115 VCE and PDF Dumps 808Q for Free Download][295-305]

2018/Aug Cisco 300-115 Exam Dumps with PDF and VCE New Updated Today! Following are some new 300-115 Real Exam Questions:1.|2018 Latest 300-115 Exam Dumps (PDF & VCE) 808Q&As

Download:<https://www.braindump2go.com/300-115.html>2.|2018 Latest 300-115 Exam Questions & Answers

Download:<https://drive.google.com/drive/folders/0B75b5xYLjSSNYjV4eHQ4dTJoQXc?usp=sharing>QUESTION 295 Which two statements are true about Option 82? (Choose two.)A. Layer 2 ingressB. Layer 3 egressC. Layer 3 ingressD. Layer 2 egressE.

Layer 4 egressF. Layer 4 ingressAnswer: ABExplanation: Layer 2 ingress → "Enters interface configuration mode, where slot/port is the Layer 2 Ethernet ingress interface where you want to configure the option 82 string." (see "Enabling or Disabling Option 82 User Defined Data Insertion and Removal") <<ingress (in) Layer 3 egress → this sounds right"; Enters interface configuration mode, where slot/port is the interface for which you want to enable or disable subnet broadcast support for the DHCP relay agent. (see "Enabling or Disabling Subnet Broadcast Support for the DHCP Relay Agent on a Layer 3 Interface") <<egress (out)

[http://www.cisco.com/c/en/us/td/docs/switches/datacenter/nexus3548/sw/security/6-x/b\\_N3548\\_Security\\_Config\\_602\\_A11/b\\_N3548\\_Security\\_Config\\_602\\_A11\\_chapter\\_01011.html](http://www.cisco.com/c/en/us/td/docs/switches/datacenter/nexus3548/sw/security/6-x/b_N3548_Security_Config_602_A11/b_N3548_Security_Config_602_A11_chapter_01011.html)QUESTION 296 Which three functions does Dynamic ARP Inspection perform with invalid IP-to-MAC address bindings?A. deletesB. logsC. acceptsD. interceptsE. discardsF. bypasses

Answer: BDEQUESTION 297 Which three features can be optimized by using SDM templates?A. port securityB. trunkC. VLAN.D. accessE. DHCP snoopingF. routingAnswer: CDFQUESTION 298 If all devices on an EtherChannel are sending traffic to a single MAC address, which two methods of load balancing on the EtherChannel are preferred? (Choose two.)A. destination-MACB. dest-source-MACC. destination-IPD. source-MACE. source-IPAnswer: BDExplanation:

<http://www.cisco.com/c/en/us/td/docs/switches/lan/catalyst4500/12-2/54sg/configuration/guide/config/channel.html>

QUESTION 299 Which command is used to verify trunk native VLANs?A. show access portsB. show interfaces trunkC. show trunkD. show vlan native trunkAnswer: BExplanation: QUESTION 300 Question about configuring VLAN 10 root bridge with spanning-tree switch priority.A. spanning-tree vlan 10 root primaryB. spanning-tree vlan 10 priority 4096Answer: AB

QUESTION 301 Which information does CDP supply from connected devices? Choose three.)A. Hardware PlatformB. Interface IDC. HostnameD. Config RegisterAnswer: ABCQUESTION 302 Question about voice VLAN. (Choose two.)A. Disabled by defaultB. Enters on untrusted portC. Default CoS value of 5 for untagged.....D. Needs manual enable of portfastAnswer: AC

QUESTION 303 Question about UDLD aggressive. (Choose two.)A. UDLD messages are sent every 15 secondsB. UDLD tries to reestablish link once before declaring the link downC. When unidirectional fail is detected, port state is determined by spanning treeD. When unidirectional fail is detected, port is turned to errdisableE. UDLD sends messages four times the message interval by defaultF. UDLD automatically ... message interval based on configured timersAnswer: ADQUESTION 304 How to configure dynamic ARP inspection on a VLAN?A. (config)# ip arp inspection vlanB. (config-if)# ip arp inspection vlanC. (config)# arp inspection defaultD. (config-if)# inspection arp vlanAnswer: AExplanation: Source:

<https://www.cisco.com/c/en/us/td/docs/switches/lan/catalyst6500/ios/12-2SX/configuration/guide/book/dynarp.html>

QUESTION 305 Diagram is: with 1 core, 2 DSW connected with EtherChannel, 2 ALSW, 2 PCs per ALSW. Per diagram current root for VLAN 10 is DSW2. Question is how to make DSW1 the primary root for VLAN 10. (Choose two.)A. DSW2: change bridge priority to 61440 (highest).B. DSW1: change bridge priority to 4096 (lowest).C. DSW1: change port priority but in global configuration mode.D. DSW1: change bridge priority but value is 0.E. DSW1: change bridge priority but command is priority rootAnswer: BE!!!RECOMMEND!!!1.|2018 Latest 300-115 Exam Dumps (PDF & VCE) 808Q&As

Download:<https://www.braindump2go.com/300-115.html>2.|2018 Latest 300-115 Study Guide Video: YouTube Video:

[YouTube.com/watch?v=4W-ViAE8YUI](https://www.youtube.com/watch?v=4W-ViAE8YUI)